

DEVICE FOR SOUNDING OF BUILDING
STRUCTURES AND WORKS

RASCAN-5/4000 (7000)

SOFTWARE MANUAL

CERTIFICATE

© TS-Market

Contents

Installing RASCAN-Q	3
File Types and Extensions.....	4
User Interface	4
Device operation.....	10
Device testing	14
Images Editing.....	16
Correcting Action	16
Additional Possibilities	26
Exporting Images to Other File Formats.....	29

RASCAN-5 is shipped with RASCAN-Q program intended for:

- operation of the device;
- receiving the images in the surface of survey for detection and identification of hidden objects (scanning);
- processing of the received images.

RASCAN-Q can be run on Windows 7, XP, Vista.

Installing RASCAN-Q


1. Insert the RASCAN-Q CD into your computer's CD drive (the control unit should be turned off and disconnected).
2. Install USB driver from FTDI folder of the CD.
3. Restart the computer.
4. Connect the control unit to the PC and turn it on.
5. Run (with Administrator rights) Setup.exe from the CD and follow on-screen instructions.

File Types and Extensions

RASCAN-Q assigns *.dbi file extension as default to identify the data files.

User Interface





RASCAN-Q has a multiple document interface whose windows reside under a single parent window.



Command List

The menu commands are listed in the table. Some items are correspond to the toolbar icons.

“File” menu

Command	Description
 Scan (Ctrl+N)	Acquire a new image (see topic “Scanning”)
 Open (Ctrl+O)	Open an existing image (data file).
 Save (Ctrl+S)	Save the image from the active window.
 Save as	Save the image from the active window under a new name. The image may also be saved to many different file formats (see topic “Exporting Images to Other File Formats”).
Exit (Ctrl+X)	Exit the program

“Edit” menu

Command

Description



Copy

Copy the image from active window to the clipboard using bitmap format. After that this image can be used by any Windows program (see topic “Image window”).



Open
(Ctrl+O)

Open an existing image (data file).



Crop

Crop the image (see topic “Cropping”)

“View” menu

Zoom In (Ctrl+ +)

Increase the scale of the image by 25 percent. You can also use the mouse wheel.

Zoom Out (Ctrl+ -)

Decrease the scale of the image by 25 percent. You can also use the mouse wheel.





Normal size
(Ctrl+D)

Display the image with original size (zoom factor equals 1).

Fit to Window

Choose, will (or not) the image be adjusted to the window while this size is changed by mouse.

“Image” menu

Command	Description
 Info	See information about active image (see topic «Image info»).
 Graphic	See image intensity distribution along any row or column (see topic “Graphic”).
 Open (Ctrl+O)	Open an existing image (data file).
 Crop	Crop the image (see topic “Cropping”)

“Device” menu

Rascan-5/7000	Choose 7 GHz device (if you have it).
---------------	---------------------------------------

“Window” menu

Close	Close current window
Close all	Close all windows
Tile	See windows side by side
Cascade	See windows stacked when the window sstack on top of each other and each window is shifted down just enough so you can see the name at the top of the window .
Next	Move the focus to the next window.
Previous	Move the focus to the previous window.

“Language” menu


Command	Description
English	Choose English for program interface (restart is required).

“Help” menu

Help	See RASCAN-Q help system
About	See information about RASCAN-Q program
About Qt	See information about Qt library

Status bar

In the bottom of the main window you can see the Status bar.




While you move mouse over image window the Status bar shows the following information:

- mouse pointer coordinates (X and Y) in pixels (and in millimeters in brackets);
- intensity (A) of the signal in current point of the image (ADC values);
- minimal and maximal values of the image intensity;
- width and height of the image in pixels.

Image Window

RASCAN-Q main window can contain any number of child windows with images acquired by RASCAN-5 radar.



Each image window is divided into two parts: left side shows the real part of the registered signal (I-quadrature) and right one shows the image part (Q-quadrature). Left clicking on the image sets the image to active state (font of the title of the active image become bold). While clicking Edit>Copy just the active image goes to the Clipboard. Also for copying the image you can click on it with right button and choosing Copy from context menu.

There is a frequency switch in the top-left corner of the image window. You can choose any frequency from multifrequency image. The switch displays number of the frequency and its value.


By clicking Process button (top-right corner) the image processing procedure is started (see topic "Image focusing").

Device operation

Please note! After turning on the device please give it about 5 minutes for warm-up.



For scanning run RASCAN-Q program and choose File>Scan (or click icon in the Toolbar). You will see a Device window.




If the device isn't connected to the computer or switched off, you will see "Waiting for connection..." text in the bottom of the window. After switching on the device the text will be changed to "Ready...". If the device is connected to the computer or switched on the text will be "Ready..." at once.

Different materials have different reflective properties. Therefore you have to calibrate the device before work on each specific site. For calibration you should press the device head to any place on scanning surface (supposedly without subsurface objects) and click Calibration button. Calibration will take a split second.

The following few parameters should be checked to ensure that they are optimal for your specific site:

- Image width in centimeters
- Image height in centimeters
- Step on OX axis
- Step on OY axis
- Starting position. If it is planning that position of the first scan line will not correspond to zero on a ruler for vertical marking, here you should specify this nonzero value.

By clicking Start button the new window will appear. Each small blue rectangle is correspond to the one pixel of the future image.



Place the head of the device onto the top-left corner (relative to operator) of scan area. Press and release Start line button (on the head) and slide the head smoothly along current scan line. When end of line is reached a beep comes and the resulting line is appeared in the image. Relocate the head to the beginning of the next line (one step from the previous). Press Start line and repeat the same routine. Motion should be smooth and straight and not too fast. A single line should be scanned for no less than 1...1.5 seconds. Use ruler or mark out surface in advance to keep lines parallel and properly spaced. You can check the number of current line in Current line at section of the Device window.


When scanning uneven surfaces use thin (2...3 mm) plexiglass sheet.

If you don't want to scan all planned lines you can finish the scanning by clicking Stop button. In this case the image height will be equal to the height of the actually scanned area.


Operator could make mistakes while scanning. For example, he could press the head to the surface too strongly or too faintly, move the head too fast or make a mistake with initial position of the head. So, in RASCAN-Q it is possible to replace last scan line. For replacing click Replace last line button in Replace line section. When scanning is finished it is possible to replace any line in the image. To do this you should move the mouse pointer to the line you want to replace and look at its number in the Status bar. Then you have to specify this number in Replace line section, click Replace line # button, move the head to the replaced line and do the scan. By clicking Finish button you confirm that current image is complete. After that you can't replace lines.


Data displayed on the computer screen will be lost when RASCAN-Q is closed. To permanently save your data, you must click File>Save, locate


the folder in which you want to save the file, type a filename in the File name list box and click Save button.

You can add short text (with experimental conditions or something else) to the data file. Choose Image>Info (or icon  in the Toolbar) and write down the text in the Description box. Then click Save button.

Device testing

Rascan-Q provides an optional routine to test the radar. To enter the test mode, open the window «Test» by choosing File>Scanning or by clicking icon  in the Toolbar. Before testing the device calibration is required as it is in the case of scanning (see topic «Scanning»). Also you can calibrate the device by pressing «Calibrate» button in the bottom left corner of the window «Test».



To start the test click  in the top-left corner, to stop the test click .

The same window has graphic symbols depicting the states of the Start Line Button and the Marching Wheel.

The amplitudes of registered signal quadratures are shown in the center of the window as a strip chart. One can choose the displayed frequency by using the spinner at the top right corner of the window. The value in spinner Delay defines the sampling interval of incoming data. The default value of the sampling interval is not required to be modified in most cases.

The testing is performed to check connections of the device and its operation. This mode can also be used to estimate penetration capability into material at hand. For example, one may place the sensor head on a sample pointing into it and wave his hand on the opposite side to check if there are visible oscillations of the signal. Oscillations with high amplitude evidence good penetration into the medium and leave good chances of acquiring images with visible subsurface objects at scanning. When signal oscillations are absent, acquiring clear images is doubtful. Alternatively, by moving the radar head within the area of interest, observable oscillations in test mode provide

information on present anomalies in the material. The receiver of the device includes an amplifier with programmable gain factor (possible values are: 1, 2, 4, 8, 16, 32, 64, 128). It is possible to set individual gain factor for each frequency. Gain factor is programmed through "Gainfactor" control in the bottom left corner. When you switch the frequencies, the current gain factor for each frequency is displayed. After choosing the new appropriate value you should store the new gain factor by pressing button "Set". If the test is started the gain factor is set only for active frequency. If the test is stopped the equal gain factor is set for all frequencies. By default the device has optimal gain factor. You can be faced with the need to change the gain factor very seldom in case of off-scale reading.

Images Editing

Correcting Action


Sometimes acquired images contain some defects. They could be caused by operator actions or (very rarely) by electromagnetic interference. If the defects were not corrected during scanning (by "Replace line" procedure) you can correct them at

any time. It is possible to correct one pixel, whole row or whole column.

Correction procedure is started by double clicking (left button) on wanted pixel of the image. At that it is convenient to increase the size of the image. If you want to edit the pixel, click exactly this pixel. If you want to edit row or column you may click any pixel of this row or column.

After clicking, the window will be opened where you can choose the subject of editing and action.


Edit pixel



As new value of the pixel you can choose:

- Mean value of neighbor on the left and on the right
- Mean value of neighbor on the top and on the bottom
- Mean value of all neighbors.

Edit row




When editing the row you have the following possibilities:

- Set new value of each pixel of the row as mean value of neighbor on the top and on the bottom
- Shift the row one pixel left
- Shift the row one pixel left.

Last two possibilities is usually used to correct the effect of wrong initial position of the head during scanning.

Edit column





When editing the row you have only possibility to set new value of each pixel of the column as mean value of neighbor on the left and on the right.

Cropping


You can crop an image to remove unwanted areas. Cropping allows you to select a rectangular area that you want to keep and discard the rest.

To crop an image:

1. Choose Image>Crop or click icon  in the Toolbar.
2. Drag to select an area on the image.
3. Press ENTER button on the keyboard.




Initial image with selected area



The image after cropping


Edit column

The image immediately registered by the radar is not exactly an image that describes actual distribution of reflectors in the space behind the sounding plane. What radar registers is an interference pattern created by these reflectors that is also called a hologram. For a distant object its interference pattern has a form of ripples due to diffraction. The diffraction effects, being stronger for a more distant object than for a closer one, may prevent a concealed object from identification.



Raw image

To compensate for diffraction effects RASCAN-Q software provides a focusing procedure that can be relied on when sounding relatively homogeneous media. Click Process button in any window with an acquired image to display the following dialog with processing parameters.




Range section has three input fields with the titles: From, To, and Step. The first two parameters define an interval of focusing depths. The third parameter defines the step between adjacent planes of focusing. It is also required to define dielectric permittivity of the medium according to the reference table given below. The discrepancy

between the permittivity value given as parameter and the actual one leads to a greater error in the focusing depth but not visually alter the result of focusing.

Material	Dielectric constant
Air	1
Ice	4
Asphalt	5
Dry concrete	5,5
Wet granite	6,5
Wet concrete	12,5
Dry sand	4
Coal	4,5
Dry granite	5
Dry limestone	5,5
Wet limestone	8
Water	81

Button Select Background allows the user to designate specific area on the image to be taken as the background. If the background is not selected manually the average intensity of image is taken, which is appropriate in many cases. A rectangular background area is chosen by performing the following sequence on an image: left mouse button press and hold->drag->left mouse button release after pressing button Select Background. The focusing starts at clicking Start button with displaying the result of focusing to a minimum depth of the depth focusing interval.



The depth of focusing can be interactively changed in edit field Depth. The desirable result of focusing procedure is to find a depth with the sharpest image. This image is best suited to identify the object of interest as compared to raw images. It should be noted that obtained estimation of depth has errors defined by inaccuracy of dielectric constant value and may not reflect the actual depth of the object.





Image focused at true depth


If the area of interest has several concealed objects at different depths, the focusing may reveal several depths in a sequence where these objects become focused. Stacked concealed objects present a difficulty to the radar due to the fact that closer objects always shield the deep. The result of focusing in such a situation prone to errors and depends on many factors that can not be taken into account.

The result of focusing can be saved as a standard image of a table of values. For further information on that please see topic “Exporting Images to Other File Formats”.

Additional Possibilities

Image info


To view full information about image choose Image>Info or click icon  in the Toolbar.




In Image info window you can view image properties, such as date of creation (could be changed), steps on 0X and 0Y axes (for research purpose could be changed), and image dimensions in pixels.


Below, you can see or fill out the Description box. In the right part of the window you can see the table where for each frequency the minimal and maximal values of the signal (and difference between maximum and minimum in brackets) are appeared. You can estimate which frequency is optimal for this experiment.



Graphic

For more detailed image analysis RASCAN-Q can plot a relation between image brightness and longitudinal or transversal coordinate (hereafter referred to as Graphis). Choose View>Graphic or click icon in  the Toolbar to see Graphis window.



Initially you see graphic along the first row of the image. Use arrows in the top-left corner to choose another rows. Current line is marked on the image by red color.



If you change the frequency by frequency switch the graphic is redrawn (the same is for depth switch if graphic is plotted for the results of processing). If you want to see dependance along column, click icon . For returning back to the row, click . If Autoscale check box is in checked state the Y axis limits are automatically changed according the values of the signal. In unchecked state you can change the limits by mouse wheel. Also you can change the zero position by moving the mouse while left button is pressed.

Exporting Images to Other File Formats

You can export RASCAN-5 images to a variety of file formats. The file format you choose depends on how you want to use the image in the future. For example, if you want to work on an image in another image editing application or to insert it into your report, you can export it to the graphical file format (*.png, *.jpg, *.tif, *.bmp). These formats are suitable because they are standard formats; images in these formats can be opened in most image viewers and most image editing and desktop publishing applications. If you want to process an image with MathCAD, MATLAB and so on, you can

export it to the *.csv format. Also you can easily open CSV file by Microsoft Excel.

Each RASCAN-5 data file stores real and imaginary parts of signals registered on all operating frequencies. For five frequencies data file contains ten images. Being exported each image is saved to an individual file. For example, if original file wires.dbi save to JPG format, there will be ten files of wires_X_YY.jpg sort, where X means real or imaginary part of the signal (1 — real part, 2 — imaginary part) and YY is frequency number.

To export an image to another file format:

1. Choose File>Save As.
2. Choose a file format from the Save as type list box.
3. Choose the folder where you want to save the file.
4. Type a filename in the File name list box.
5. Click Save.